

STANDARD OPTIONS	NON-STANDARD OPTIONS	ADVANCED OPTIONS	
		BEHAVIOR	PERFORMANCE
\$ java List all standard options.	\$ java -X List all non-standard options.	-XX:+UseConcMarkSweepGC Enables CMS garbage collection.	-XX:ThreadStackSize=256k Sets Thread Stack Size (in bytes). (Same as -Xss256k)
-Dblog=JRebelBlog Sets a 'blog' system property to 'JRebelBlog'. Retrieve/set it during runtime like this:	-Xint Runs the application in interpreted-only mode.	-XX:+UseParallelGC Enables parallel garbage collection.	-XX:G1HeapRegionSize=4m Sets the sub-division size of G1 heap (in bytes).
System.setProperty("blog"); <code>//JRebelBlog</code>	-Xbootclasspath:path Path and archive list of boot class files.	-XX:+UseSerialGC Enables serial garbage collection.	-XX:MaxGCPauseMillis=n Sets a target for the maximum GC pause time.
System.setProperty("blog", "JR");	-Xloggc:filename Log verbose GC events to filename.	-XX:+UseG1GC Enables G1GC garbage collection.	-XX:MaxNewSize=256m Max size of new generation (in bytes).
-javaagent:/path/to/agent.jar Loads the java agent in agent.jar.	-Xms1g Set the initial size (in bytes) of the heap.		-XX:OnError=<cmd args>" Run user-defined commands on fatal error.
-agentpath:pathname Loads the native agent library specified by the absolute path name.	-Xmx8g Specifies the max size (in bytes) of the heap.	-XX:ErrorFile=file.log Save the error data to file.log.	
-verbose:[class/gc/jni] Displays information about each loaded class/gc event/JNI activity.	-Xnoclassgc Disables class garbage collection.	-XX:+HeapDumpOnOutOfMemoryError Enables heap dump when <code>OutOfMemoryError</code> is thrown.	
	-Xprof Profiles the running program.	-Xlog:gc Enables printing messages during garbage collection.	
		-XX:+TraceClassLoading Enables Trace loading of classes.	
		-XX:+PrintClassHistogram Enables printing of a class instance histogram after a <code>Control+C</code> event (<code>SIGTERM</code>).	